

Standard Letter Document Class for L^AT_EX version 2e

Leslie Lamport and Frank Mittelbach and Rainer Schöpf

August 22, 2024

This file is maintained by the L^AT_EX Project team.
Bug reports can be opened (category `latex`) at
<https://latex-project.org/bugs.html>.

Contents

1 Initial Code	2
1.1 Setting Paper Sizes	2
1.2 Choosing the type size	3
1.3 Two-side or one-side printing	3
1.4 Draft option	3
1.5 Equation numbering on the left	3
1.6 Flush left displays	4
2 Executing Options	4
3 Loading Packages	4
4 Document Layout	4
4.1 Paragraphing	4
4.2 Page Layout	5
4.2.1 Vertical spacing	5
4.2.2 The dimension of text	5
4.2.3 Margins	6
4.2.4 Footnotes	6
4.3 Page Styles	7
4.3.1 Marking conventions	7
4.3.2 Defining the page styles	7
5 Document Markup	8
5.1 Global Declarations	8
5.2 The generic letter commands	9
5.2.1 Page breaking control	10
5.3 Customizing the labels	13
5.4 Lists	15

5.4.1	General List Parameters	15
5.4.2	Enumerate	16
5.4.3	Itemize	16
5.4.4	Description	17
5.5	Defining new environments	17
5.5.1	Verse	17
5.5.2	Quotation	17
5.5.3	Quote	18
5.5.4	Theorem	18
5.6	Setting parameters for existing environments	18
5.6.1	Array and tabular	18
5.6.2	Tabbing	18
5.6.3	Minipage	18
5.6.4	Framed boxes	19
5.6.5	Equation and eqnarray	19
5.7	Font changing	19
5.8	Footnotes	20
6	Initialization	21
6.1	Words	21
6.2	Date	21
6.3	Two column mode	21
6.4	The page style	21
6.5	Single or double sided printing	21

1 Initial Code

In this part we define a few commands that are used later on.

\@ptsize This control sequence is used to store the second digit of the pointsize we are typesetting in. So, normally, it's value is one of 0, 1 or 2.

```
1 <*letter>
2 \newcommand{\@ptsize{}}
```

1.1 Setting Paper Sizes

The variables \paperwidth and \paperheight should reflect the physical paper size after trimming. For desk printer output this is usually the real paper size since there is no post-processing.

```
3 \DeclareOption{a4paper}
4   {\setlength{\paperheight}{297mm}%
5    \setlength{\paperwidth}{210mm}}
6 \DeclareOption{a5paper}
7   {\setlength{\paperheight}{210mm}%
8    \setlength{\paperwidth}{148mm}}
9 \DeclareOption{b5paper}
10  {\setlength{\paperheight}{250mm}%
11   \setlength{\paperwidth}{176mm}}
12 \DeclareOption{letterpaper}
13  {\setlength{\paperheight}{11in}}%
```

```

14   \setlength\paperwidth {8.5in}
15 \DeclareOption{legalpaper}
16   {\setlength\paperheight {14in}%
17   \setlength\paperwidth {8.5in}}
18 \DeclareOption{executivepaper}
19   {\setlength\paperheight {10.5in}%
20   \setlength\paperwidth {7.25in}}

```

The option `landscape` switches the values of `\paperheight` and `\paperwidth`, assuming the dimensions were given for portrait paper.

```

21 \DeclareOption{landscape}
22   {\setlength{@tempdima} {\paperheight}%
23   \setlength\paperheight {\paperwidth}%
24   \setlength\paperwidth {\@tempdima}}

```

1.2 Choosing the type size

The type size options are handled by defining `\@ptsize` to contain the last digit of the size in question and branching on `\ifcase` statements. This is done for historical reasons to stay compatible with other packages that use the `\@ptsize` variable to select special actions. It makes the declarations of size options less than 10pt difficult, although one can probably use 9 and 8 assuming that a class wont define both 8pt and 18pt options.

```

25 \DeclareOption{10pt}{\renewcommand{\@ptsize{0}}}
26 \DeclareOption{11pt}{\renewcommand{\@ptsize{1}}}
27 \DeclareOption{12pt}{\renewcommand{\@ptsize{2}}}

```

1.3 Two-side or one-side printing

Two-sided printing was not supported in the L^AT_EX 2.09 version of this document class.

```

28 \if@compatibility
29   \DeclareOption{twoside}{\@latexerr{No 'twoside' layout for letters}%
30                           \@eha}
31 \else
32   \DeclareOption{twoside}{\@twosidetrue \c@mparswitchtrue}
33 \fi
34 \DeclareOption{oneside}{\@twosidefalse \c@mparswitchfalse}

```

1.4 Draft option

If the user requests `draft` we show any overfull boxes. We could probably add some more interesting stuff to this option.

```

35 \DeclareOption{draft}{\setlength\overfullrule{5pt}}
36 \DeclareOption{final}{\setlength\overfullrule{0pt}}

```

1.5 Equation numbering on the left

The option `leqno` can be used to get the equation numbers on the left side of the equation.

```

37 \DeclareOption{leqno}{\input{leqno.clo}}

```

1.6 Flush left displays

The option `fleqn` redefines the displayed math environments in such a way that they come out flush left, with an indentation of `\mathindent` from the prevailing left margin.

```
38 \DeclareOption{fleqn}{\input{fleqn.clo}}
```

2 Executing Options

Here we execute the default options to initialize certain variables.

```
39 \ExecuteOptions{letterpaper,10pt,oneside,onecolumn,final}
```

The `\ProcessOptions` command causes the execution of the code for every option `foo` which is declared and for which the user typed the `foo` option in his `\documentclass` command. For every option `bar` he typed, which is not declared, the option is assumed to be a global option. All options will be passed as document options to any `\usepackage` command in the document preamble.

```
40 \ProcessOptions
```

Now that all the options have been executed we can load the chosen class option file that contains all size dependent code.

```
41 \input{size1@ptsize.clo}
```

3 Loading Packages

The standard class files do not load additional packages.

4 Document Layout

In this section we are finally dealing with the nasty typographical details.

4.1 Paragraphing

`\lineskip` These parameters control T_EX's behavior when two lines tend to come too close `\normallineskip` together.

```
42 \setlength{\lineskip}{1\p@}  
43 \setlength{\normallineskip}{1\p@}
```

`\baselinestretch` This is used as a multiplier for `\baselineskip`. The default is to *not* stretch the baselines.

```
44 \renewcommand{\baselinestretch}{}
```

`\parskip` `\parskip` gives extra vertical space between paragraphs and `\parindent` is the `\parindent` width of the paragraph indentation. Letters are typeset without paragraph indentation.

```
45 \setlength{\parskip}{0.7em}  
46 \setlength{\parindent}{0\p@}
```

\@lowpenalty The commands `\nopagebreak` and `\nolinebreak` put in penalties to discourage
\@medpenalty these breaks at the point they are put in. They use `\@lowpenalty`, `\@medpenalty`
\@highpenalty or `\@highpenalty`, dependent on their argument.

```
47 \@lowpenalty 51
48 \@medpenalty 151
49 \@highpenalty 301
```

\clubpenalty These penalties are used to discourage club and widow lines. Because we use their
\widowpenalty default values we only show them here, commented out.

```
50 % \clubpenalty 150
51 % \widowpenalty 150
```

\displaywidowpenalty Discourage (but not so much) widows in front of a math display and forbid break-
\predisplaypenalty ing directly in front of a display. Allow break after a display without a penalty.
\postdisplaypenalty Again the default values are used, therefore we only show them here.

```
52 % \displaywidowpenalty 50
53 % \predisplaypenalty 10000
54 % \postdisplaypenalty 0
```

\interlinepenalty Allow the breaking of a page in the middle of a paragraph.

```
55 % \interlinepenalty 0
```

\brokenpenalty We allow the breaking of a page after a hyphenated line.

```
56 % \brokenpenalty 0
```

4.2 Page Layout

All margin dimensions are measured from a point one inch from the top and lefthand side of the page.

4.2.1 Vertical spacing

\headheight The `\headheight` is the height of the box that will contain the running head. The
\headsep `\headsep` is the distance between the bottom of the running head and the top of
the text. `\topskip` is the `\baselineskip` for the first line on a page, its value
depends on the size option that was specified. Therefore it is initialized in one of
the `size1x.clo` files.

```
57 \setlength\headheight{12\p@}
58 \setlength\headsep {45\p@}
```

\footskip The distance from the baseline of the box which contains the running footer to
the baseline of last line of text is controlled by the `\footskip`. Bottom of page:

```
59 \setlength\footskip{25\p@}
```

4.2.2 The dimension of text

\textwidth When we are in compatibility mode we have to make sure that the dimensions of
the printed area are not different from what the user was used to see.

```
60 \if@compatibility
61   \setlength\textwidth{365\p@}
```

\textheight Now that we have computed the width of the text, we have to take care of the height. The **\textheight** is the height of text (including footnotes and figures, excluding running head and foot).

```
62 \setlength\textheight{505\p@}  
63 \fi
```

In native mode we use the dimensions as they were computed by one of the **xxpt** options, together with one of the **.paper** options.

4.2.3 Margins

\oddsidemargin The values of **\oddsidemargin** and **\evensidemargin** are computed from those **\evensidemargin** of **\paperwidth** and **\textwidth**.

```
\marginparwidth 64 \if@compatibility  
65 \setlength\oddsidemargin{53pt}  
66 \setlength\evensidemargin{53pt}  
67 \setlength\marginparwidth{90pt}  
68 \else  
69 \setlength\@tempdima{\paperwidth}  
70 \addtolength\@tempdima{-2in}  
71 \addtolength\@tempdima{-\textwidth}  
72 \setlength\oddsidemargin {5\@tempdima}  
73 \setlength\evensidemargin {\oddsidemargin}  
74 \setlength\marginparwidth {90\p@}  
75 \fi
```

\marginparsep The horizontal space between the main text and marginal notes is determined by **\marginparpush** **\marginparsep**, the minimum vertical separation between two marginal notes is controlled by **\marginparpush**.

```
76 \setlength\marginparsep {11\p@}  
77 \setlength\marginparpush{5\p@}
```

\topmargin The **\topmargin** is the distance between the top of ‘the printable area’ –which is 1 inch below the top of the paper– and the top of the box which contains the running head.

It can now be computed from the values set above.

```
78 \setlength\topmargin{27pt}
```

4.2.4 Footnotes

\footnotesep **\footnotesep** is the height of the strut placed at the beginning of every footnote. It equals the height of a normal **\footnotesize** strut in this class, thus no extra space occurs between footnotes.

```
79 \setlength\footnotesep{12\p@}
```

\footins **\skip\footins** is the space between the last line of the main text and the top of the first footnote.

```
80 \setlength{\skip\footins}{10\p@ \oplus 2\p@ \minus 4\p@}
```

4.3 Page Styles

The page style *foo* is defined by defining the command `\ps@foo`. This command should make only local definitions. There should be no stray spaces in the definition, since they could lead to mysterious extra spaces in the output (well, that's something that should be always avoided).

`\@evenhead` The `\ps@...` command defines the macros `\@oddhead`, `\@oddfoot`, `\@evenhead`, `\@oddhead` and `\@evenfoot` to define the running heads and feet—e.g., `\@oddhead` is the `\@evenfoot` macro to produce the contents of the heading box for odd-numbered pages. It is `\@oddfoot` called inside an `\hbox` of width `\textwidth`.

4.3.1 Marking conventions

To make headings determined by the sectioning commands, the page style defines the commands `\chaptermark`, `\sectionmark`, ..., where `\chaptermark{<text>}` is called by `\chapter` to set a mark, and so on.

The `\...mark` commands and the `\...head` macros are defined with the help of the following macros. (All the `\...mark` commands should be initialized to no-ops.)

L^AT_EX extends T_EX's `\mark` facility by producing two kinds of marks, a ‘left’ and a ‘right’ mark, using the following commands:

`\markboth{<left>}{<right>}:` Adds both marks.
`\markright{<right>}:` Adds a ‘right’ mark.
`\leftmark:` Used in the `\@oddhead`, `\@oddfoot`, `\@evenhead` or `\@evenfoot` macros, it gets the current ‘left’ mark. `\leftmark` works like T_EX's `\botmark` command.
`\rightmark:` Used in the `\@oddhead`, `\@oddfoot`, `\@evenhead` or `\@evenfoot` macros, it gets the current ‘right’ mark. `\rightmark` works like T_EX's `\firstmark` command.

The marking commands work reasonably well for right marks ‘numbered within’ left marks—e.g., the left mark is changed by a `\chapter` command and the right mark is changed by a `\section` command. However, it does produce somewhat anomalous results if two `\markboth`'s occur on the same page.

Commands like `\tableofcontents` that should set the marks in some page styles use a `\@mkboth` command, which is `\let` by the `pagestyle` command (`\ps@...`) to `\markboth` for setting the heading or to `\@gobbletwo` to do nothing.

4.3.2 Defining the page styles

The pagestyles *empty* and *plain* are defined in the L^AT_EX kernel (`ltpage.dtx`), but these definitions are changed to a simpler version for this document class.

`\ps@headings` The definition of the page style *headings* has to be different for two sided printing than it is for one sided printing.

```
81 \if@twoside  
82   \def\ps@headings{%
```

The running feet are empty in this page style.

```
83   \let\@oddfoot\@empty\let\@evenfoot\@empty
```

The running head contains some information about this letter. The head is the same for even and odd pages.

```

84      \def\@oddhead{\slshape\headtoname{} \ignorespaces\tename
85          \hfil \cdate
86          \hfil \pagename{} \thepage}%
87      \let\@evenhead\@oddhead

```

For one sided printing we don't need to define \@evenhead so the definition is somewhat simpler.

```

88 \else
89   \def\ps@headings{%
90     \let\@oddfoot\empty
91     \def\@oddhead{\slshape\headtoname{} \ignorespaces\tename
92         \hfil \cdate
93         \hfil \pagename{} \thepage}%
94 \fi

```

\ps@empty The definition of the page style *empty* is simple: No running head or foot at all.

```

95 \def\ps@empty{%
96   \let\@oddfoot\empty\let\@oddhead\empty
97   \let\@evenfoot\empty\let\@evenhead\empty}

```

\ps@firstpage The page style *firstpage* puts the telephone number in the proper place for the letterhead. It should be adapted to site conventions. The size of the number is determined depending on the main size.

```

98 \def\ps@firstpage{%
99   \let\@oddhead\empty
100  \def\@oddfoot{\raisebox{-45\p@}{\textwidth{\hspace*{100\p@}}%
101    \hb@xt@\textwidth{\hspace*{100\p@}}%
102    \ifcase \@ptsize\relax
103      \normalsize
104    \or
105      \small
106    \or
107      \footnotesize
108    \fi
109    \fromlocation \hfill \telephonenum}\hss}}

```

\ps@plain The definition of the page style *plain* is again simple.

```

110 \def\ps@plain{%
111   \let\@oddhead\empty
112   \def\@oddfoot{\normalfont\hfil\thepage\hfil}%
113   \def\@evenfoot{\normalfont\hfil\thepage\hfil}}

```

5 Document Markup

5.1 Global Declarations

\name The following declarations, shown with examples, give information about the \signature sender:

```

\address   • \name{Dr. L. User} : to be used for the return address on the envelope.
\location
\telephone 114 \newcommand*\name[1]{\def\fromname{#1}}

```

- `\signature{Larry User}` : goes after the closing.
- 115 `\newcommand*\signature[1]{\def\fromsig{\#1}}`
- `\address{3245 Foo St.\Gnu York}` : used as the return address in the letter and on the envelope. If not declared, then an institutional standard address is used.
- 116 `\newcommand*\address[1]{\def\fromaddress{\#1}}`
- `\location{Room 374}` : Acts as modifier to the standard institutional address.
- 117 `\newcommand*\location[1]{\def\fromlocation{\#1}}`
- `\telephone{(415)123-4567}` : Just in case some style puts it on the letter.

118 `\newcommand*\telephone[1]{\def\telephonenum{\#1}}`

`\fromname` We make sure that the internal control sequences that are used to store the information exist and are empty.

`\fromsig` 119 `\name{}`
`\fromaddress` 120 `\signature{}`
`\fromlocation` 121 `\address{}`
`\telephonenum` 122 `\location{}`
123 `\telephone{}`

`\makelabels` The `\makelabels` declaration causes mailing labels to be made.

124 `\newcommand*\makelabels{%`

At the beginning of the document, we need to activate the `\@mlabel` and `\@startlabels` commands, as well as write `\@startlabels` to the `.aux` file.

125 `\AtBeginDocument{%`
126 `\let\@startlabels\startlabels`
127 `\let\@mlabel\mlabel`
128 `\if@filesw`
129 `\immediate\write\@mainaux{\string\@startlabels}\fi}%`

At the end of the document we need to write `\clearpage` to the `.aux` file.

130 `\AtEndDocument{%`
131 `\if@filesw\immediate\write\@mainaux{\string\clearpage}\fi}}`

`\makelabels` is allowed only before the `\begin{document}` command.

132 `\onlypreamble\makelabels`

5.2 The generic letter commands

`letter (env.)` The letter environment creates a new letter, starting from page 1, with footnotes starting from 1 as well. (The first page is unnumbered.) It has a single argument, which is the addressee and his address, as in

```
\begin{letter}{Sam Jones \\
Institute for Trivial Study\\
Princeton, N.J.}
```

Local declarations, such as `\address`, can follow the `\begin{letter}`.

```
133 \newenvironment{letter}[1]
134   {\newpage
135     \if@twoside \ifodd\c@page
136       \else\thispagestyle{empty}\null\newpage\fi
137     \fi
138     \c@page \c@ne
139     \c@footnote \z@
140     \interlinepenalty=200 % smaller than the TeXbook value
```

The `\leavevmode` and `\ignorespaces` commands are there for protecting against an empty argument.

```
141   \g@processsto{\leavevmode\ignorespaces #1}}
```

The end of the environment possibly writes the address information on the `.aux` file.

```
142   {\stopletter\@@par\pagebreak\@@par
143     \if@filesw
144       \begingroup
145         \let\\=\relax
146         \let\protect\@unexpandable@protect
147         \immediate\write\@auxout{%
148           \string\@label{\returnaddress}{\toname\\\toaddress}}%
149       \endgroup
150     \fi}
```

`\g@processsto` gets the `\toname` and `\toaddress` from the letter environment's `\@xproc` macro argument. `\@xproc` and `\@yproc` are auxiliary macros.

```
\@yproc 151 \long\def\@processo#1{%
152   \@xproc #1\@%
153   \ifx\toaddress\empty
154   \else
155     \@yproc #1@%
156   \fi}
157 \long\def\@xproc #1\@#2@{\def\toname{#1}\def\toaddress{#2}}
158 \long\def\@yproc #1\@#2@{\def\toaddress{#2}}
```

5.2.1 Page breaking control

`\stopbreaks` When the command `\stopbreaks` is issued no page breaks should occur until `\startbreaks` is called.

```
159 \newcommand*\stopbreaks{%
160   \interlinepenalty\@M
161   \def\par{\@par\nobreak}%
162   \let\\@nobreakcr
163   \let\vspace\@nobreakvspace}
```

`\nobreakvspace` These are needed by `\stopbreaks`

```
\@nobreakvspace 164 \DeclareRobustCommand\@nobreakvspace
\@nobreakcr 165   {\@ifstar\@nobreakvspace\@nobreakvspace}
166 \def\@nobreakvspace#1{%
167   \ifvmode
```

```

168     \nobreak\vskip #1\relax
169 \else
170     \@bsphack\vadjust{\nobreak\vskip #1}\@esphack
171 \fi}

172 \def\@nobreakcr{\@ifstar{\@normalcr*}{\@normalcr*}}

```

`\startbreaks` This cancels the effect of `\stopbreaks`.

```

173 \newcommand*\startbreaks{%
174   \let\\@\\normalcr
175   \interlinepenalty 200%
176   \def\par{\@@par\penalty 200\relax}}

```

`\longindentation` The size of the indent to use before the closing of the letter.

```

177 \newdimen\longindentation
178 \longindentation=.5\textwidth

```

`\indentedwidth` The width of the closing of the letter.

```

179 \newdimen\indentedwidth
180 \indentedwidth=\textwidth
181 \advance\indentedwidth -\longindentation

```

`\opening` Text is begun with the `\opening` command, whose argument generates the salutation, as in

```
\opening{Dear Henry,}
```

This should produce everything up to and including the ‘Dear Henry,’ and a `\par` command that follows. Since there’s a `\vfil` at the bottom of every page, it can add vertical fill to position a short letter. It should use the following commands:

- `\toname` : name part of ‘to’ address. Will be one line long.
- `\toaddress` : address part of ‘to’ address. The lines separated by `\\"`.
- `\fromname` : name of sender.
- `\fromaddress` : argument of current `\address` declaration– null if none. Should use standard institutional address if null.
- `\fromlocation` : argument of current `\location` declaration–null if none.
- `\telephonenum` : argument of current `\telephone` declaration–null if none.

```

182 \newcommand*\opening[1]{\ifx\@empty\fromaddress
183   \thispagestyle{firstpage}%
184   {\raggedleft\@date\par}%
185 \else % home address
186   \thispagestyle{empty}%
187   {\raggedleft\begin{tabular}{l@{} }\ignorespaces
188     \fromaddress \\*[2\parskip]%
189     \@date \end{tabular}\par}%
190 \fi
191 \vspace{2\parskip}%

```

If the address field used `\\"[...]` then we have `\toaddress` starting with the bracket argument as the split was done simply at `\\".` So we add `\expandafter` here so that is will be used and not typeset. A better fix would be to do a proper parsing but ...

Other classes based on `letter.cls` could benefit from the same fix, e.g., `akletter.cls`, `bletter.cls`, `letter.cls`, `chletter.cls`, `extletter.cls`, `frletter.cls`, `hletter.cls`, `scrlttr2.cls` (change rejected), `lettre.cls`, `beletter.cls`, `brief.cls` and perhaps others.

```
192  {\raggedright \toname \expandafter\\toaddress \par}%
193  \vspace{2\parskip}%
194  #1\par\nobreak}
```

`\closing` The body of the letter follows, ended by a `\closing` command, as in

```
\closing{Yours truly,}
```

This command generates the closing matter, and the signature. An obvious thing to do is to use a `\parbox` for the closing and the signature. Should use the following:

- `\fromsig` : argument of current `\signature` declaration or, if null, the `\fromname`.
- `\stopbreaks` : a macro that inhibits page breaking.

```
195 \newcommand{\closing}[1]{\par\nobreak\vspace{\parskip}%
196   \stopbreaks
197   \noindent
198   \ifx\@empty\fromaddress\else
199     \hspace*{\longindentation}\fi
200   \parbox{\indentedwidth}{\raggedright
201     \ignorespaces #1\\[6\medskipamount]%
202     \ifx\@empty\fromsig
203       \fromname
204     \else \fromsig \fi\strut}%
205 }
```

`\smallskipamount` Of these three, only `\medskipamount` is actually used above.

```
\medskipamount 206 %\smallskipamount=.5\parskip
\bigskipamount 207 \medskipamount=\parskip
208 %\bigskipamount=2\parskip
```

`\cc` After the `\closing` you can put arbitrary stuff, which is typeset with zero `\encl` `\parindent` and no page breaking. Commands designed for use after the closing are:

```
\cc{Tinker\Evers\Chance}
```

which produces:

```
cc: Tinker
      Evers
      Chance
```

Note the obvious use of `\parbox`.

```

209 \newcommand*{\cc}[1]{%
210   \par\noindent
211   \parbox[t]{\textwidth}{%
212     \hangfrom{\normalfont\ccname: }%
213     \ignorespaces #1\strut}\par}
214 \encl{Foo(2)\Bar}

```

which produces:

```

encl: Foo(2)
      Bar

```

```

214 \newcommand*{\encl}[1]{%
215   \par\noindent
216   \parbox[t]{\textwidth}{%
217     \hangfrom{\normalfont\enclname: }%
218     \ignorespaces #1\strut}\par}

```

The only thing `\ps` needs to do is call `\startbreaks`, which allows page breaking again.

```
219 \newcommand*{\ps}{\par\startbreaks}
```

`\stopletter` The `\stopletter` command is called by `\endletter` to do the following:

- Add any desired fill or other material at the end of the letter.
- Define `\returnaddress` to be the return address for the mailing label. More precisely, it is the first argument of the `\mlabel` command described below. It should be defined to null if the return address doesn't appear on the labels. Any command, other than `\backslash`, that should not be expanded until the `\mlabel` command is actually executed must be preceded by `\protect`. Whenever possible, `\protect` commands in the definition of `\returnaddress`—it's much more efficient that way. In particular, when the standard return address is used, you should define `\returnaddress` to something like `\protect\standardreturnaddress`.

```
220 \newcommand*{\stopletter}{}%
```

5.3 Customizing the labels

Commands for generating the labels are put on the `.aux` file, which is read in and processed by the `\end{document}` command. You have to define the following two commands:

- `\startlabels` : Should reset the page layout parameters if necessary.
- `\mlabel{\<return address>}{\<to address>}` : Command to generate a single label.

`\returnaddress` The return address for the mailing labels can be stored in this macro.

```
221 \newcommand*{\returnaddress}{}%
```

`\labelcount` A register to count the labels

```
222 \newcount\labelcount
```

\startlabels The following \startlabels command sets things up for producing labels in two columns of five 2" × 4-1/4" labels each, suitable for reproducing onto Avery brand number 5352 address labels.

```
223 \newcommand*\startlabels{\labelcount\z@  
224   \pagestyle{empty}!  
225   \let\@texttop\relax  
226   \topmargin -50\p@  
227   \headsep \z@  
228   \oddsidemargin -35\p@  
229   \evensidemargin -35\p@  
230   \textheight 10in  
231   \@colht\textheight \@colroom\textheight \vsize\textheight  
232   \textwidth 550\p@  
233   \columnsep 26\p@  
234   \ifcase \@ptsize\relax  
235     \normalsize  
236   \or  
237     \small  
238   \or  
239     \footnotesize  
240   \fi  
241   \baselineskip \z@  
242   \lineskip \z@  
243   \boxmaxdepth \z@  
244   \parindent \z@  
245   \twocolumn\relax}
```

\@startlabels \@startlabels is the command name that is written to the .aux file. It is a no-op at first, and defined to be the same as \startlabels in the \begin{document} hook.

```
246 \let\@startlabels=\relax
```

\mlabel This command prints an address label; it is used when the user specified \makelabels in the preamble of his document. The command \mlabel takes two arguments; the second argument is supposed to be the address; the first argument can be used to print a return address. In this document class we ignore the first argument. Also the labels are supposed to be 2 inch high and 3.6 inch wide. When your address labels have a different you will have to define your own \mlabel command.

```
247 \newcommand*\mlabel[2]{%  
248   \parbox[b][2in][c]{262\p@}{\strut\ignorespaces #2}%  
249 }
```

\@mlabel The macro \@mlabel is written to the .aux file instead of \mlabel. This allows us to make it a no-op by default, and then activate it in the \begin{document} hook.

```
250 \let\@mlabel=\@gobbletwo
```

5.4 Lists

5.4.1 General List Parameters

The following commands are used to set the default values for the list environment's parameters. See the L^AT_EX manual for an explanation of the meanings of the parameters. Defaults for the list environment are set as follows. First, `\rightmargin`, `\listparindent` and `\itemindent` are set to 0pt. Then, for a Kth level list, the command `\@listK` is called, where 'K' denotes 'i', 'ii', ... , 'vi'. (I.e., `\@listiii` is called for a third-level list.) By convention, `\@listK` should set `\leftmargin` to `\leftmarginK`.

`\leftmargin` For efficiency, level-one list's values are defined at top level, and `\@listi` is defined `\leftmargini` to set only `\leftmargin`.

251 `\setlength{\leftmargini}{2.5em}`

`\leftmarginii` The following three are calculated so that they are larger than the sum of `\leftmarginiv` `\labelsep` and the width of the default labels (which are '(m)', 'vii.' and 'M.').

252 `\setlength{\leftmarginii}{2.2em}`

253 `\setlength{\leftmarginiii}{1.87em}`

254 `\setlength{\leftmarginiv}{1.7em}`

255 `\setlength{\leftmarginv}{1em}`

256 `\setlength{\leftmarginvi}{1em}`

Here we set the top level leftmargin.

257 `\setlength{\leftmargin}{\leftmargini}`

`\labelsep` `\labelsep` is the distance between the label and the text of an item; `\labelwidth` `\labelwidth` is the width of the label.

258 `\setlength{\labelsep}{5pt}`

259 `\setlength{\labelwidth}{\leftmargini}`

260 `\addtolength{\labelwidth}{-\labelsep}`

`\partopsep` When the user leaves a blank line before the environment an extra vertical space of `\partopsep` is inserted, in addition to `\parskip` and `\topsep`.

261 `\setlength{\partopsep}{0pt}`

`\@beginparpenalty` These penalties are inserted before and after a list or paragraph environment.

`\@endparpenalty` They are set to a bonus value to encourage page breaking at these points.

`\@itempenalty` This penalty is inserted between list items.

262 `\@beginparpenalty -\@lowpenalty`

263 `\@endparpenalty -\@lowpenalty`

264 `\@itempenalty -\@lowpenalty`

`\@listI` `\@listI` defines top level and `\@listi` values of `\leftmargin`, `\parsep`, `\topsep`, `\@listi` and `\itemsep`

265 `\def{\@listI}{\setlength{\leftmargin}{\leftmargini}}%`

266 `\setlength{\parsep}{0pt}%`

267 `\setlength{\topsep}{.4em}%`

268 `\setlength{\itemsep}{.4em}}`

269 `\let{\@listi}{\@listI}`

We have to initialize these parameters.

270 `\@listi`

```

\@listii Here are the same macros for the higher level lists.
\@listiii 271 \def\@listii {\setlength \leftmargin{\leftmarginii}%
\@listiv 272 \setlength \labelwidth{\leftmarginii}%
\@listv 273 \addtolength\labelwidth{-\labelsep}}
\@listvi 274 \def\@listiii {\setlength \leftmargin{\leftmarginiii}%
275 \setlength \labelwidth{\leftmarginiii}%
276 \addtolength\labelwidth{-\labelsep}%
277 \setlength \topsep {.2em}%
278 \setlength \itemsep {\topsep}%
279 \def\@listiv {\setlength \leftmargin{\leftmarginiv}%
280 \setlength \labelwidth{\leftmarginiv}%
281 \addtolength\labelwidth{-\labelsep}%
282 \def\@listv {\setlength \leftmargin{\leftmarginv}%
283 \setlength \labelwidth{\leftmarginv}%
284 \addtolength\labelwidth{-\labelsep}%
285 \def\@listvi {\setlength \leftmargin{\leftmarginvi}%
286 \setlength \labelwidth{\leftmarginvi}%
287 \addtolength\labelwidth{-\labelsep}}

```

5.4.2 Enumerate

The enumerate environment uses four counters: *enumi*, *enumii*, *enumiii* and *enumiv*, where *enumN* controls the numbering of the Nth level enumeration.

```

\theenumi The counters are already defined in the LATEX kernel (ltlists.dtx), but their
\theenumii representation is changed here.
\theenumii 288 \renewcommand\theenumi{\@arabic\c@enumi}
\theenumiv 289 \renewcommand\theenumii{\@alph\c@enumii}
290 \renewcommand\theenumiii{\@roman\c@enumiii}
291 \renewcommand\theenumiv{\@Alph\c@enumiv}

```

```

\labelenumi The commands \labelenumi ... \labelenumiv generate the label for each item.
\labelenumii 292 \newcommand\labelenumi{\theenumi.}
\labelenumiii 293 \newcommand\labelenumii{(\theenumii)}
\labelenumiv 294 \newcommand\labelenumiii{(\theenumiii.)}
295 \newcommand\labelenumiv{(\theenumiv.)}

```

\p@enumii The expansion of \p@enumN\theenumN defines the output of a \ref command
\p@enumiii when referencing an item of the Nth level of an enumerated list.

```

\p@enumi 296 \renewcommand\p@enumi{\theenumi}
297 \renewcommand\p@enumii{\theenumi(\theenumii)}
298 \renewcommand\p@enumiv{\p@enumiii\theenumiii}

```

5.4.3 Itemize

\labelitemi Itemization is controlled by \labelitemi, \labelitemii, \labelitemiii, and
\labelitemii \labelitemiv, which define the labels of the various itemization levels: the sym-
\labelitemiii bols used are bullet, bold en-dash, asterisk and centered dot.

```

\labelitemiv 299 \newcommand\labelitemi {\labelitemfont \textbullet}
300 \newcommand\labelitemii {\labelitemfont \bfseries \textendash}
301 \newcommand\labelitemiii {\labelitemfont \textasteriskcentered}
302 \newcommand\labelitemiv {\labelitemfont \textperiodcentered}

```

`\labelitemfont` The default definition for `\labelitemfont` is to reset the font to `\normalfont` so that always the same symbol is produced regardless of surrounding conditions.
A possible alternative would be

```
302 \renewcommand{\labelitemfont}{%
  \fontseries\seriesdefault
  \fontshape\shapedefault\selectfont}
```

which resets series and shape doesn't touch the family.

```
303 \newcommand{\labelitemfont}{\normalfont}
```

5.4.4 Description

`description (env.)` The description environment is defined here – while the itemize and enumerate environments are defined in the L^AT_EX kernel (`ltlists.dtx`).

```
304 \newenvironment{description}
305   {\list{}{\labelwidth\z@ \itemindent-\leftmargin
306             \let\makelabel\descriptionlabel}}
307   {\endlist}
```

`\descriptionlabel` To change the formatting of the label, you must redefine `\descriptionlabel`.

```
308 \newcommand*\descriptionlabel[1]{\hspace{\labelsep
309                               \normalfont\bfseries #1}}
```

5.5 Defining new environments

5.5.1 Verse

`verse (env.)` The verse environment is defined by making clever use of the list environment's parameters. The user types `\\"` to end a line. This is implemented by `\let`'ing `\\"` equal `\@centercr`.

```
310 \newenvironment{verse}
311   {\let\\=\@centercr
312   \list{}{\setlength{\itemsep}{\z@}%
313           \setlength{\itemindent}{-15\p@}%
314           \setlength{\listparindent}{\itemindent}%
315           \setlength{\rightmargin}{\leftmargin}%
316           \addtolength{\leftmargin}{15\p@}}%
317   \item[]%
318   \endlist}
```

5.5.2 Quotation

`quotation (env.)` The quotation environment is also defined by making clever use of the list environment's parameters. The lines in the environment are set smaller than `\textwidth`. The first line of a paragraph inside this environment is indented.

```
319 \newenvironment{quotation}
320   {\list{}{\setlength{\listparindent}{1.5em}%
321           \setlength{\itemindent}{\listparindent}%
322           \setlength{\rightmargin}{\leftmargin}}%
323   \item[]%
324   \endlist}
```

5.5.3 Quote

`quote (env.)` The quote environment is like the quotation environment except that paragraphs are not indented.

```
325 \newenvironment{quote}
326     {\list{}{\setlength\rightmargin{\leftmargin}%
327         \item[]}
328     {\endlist}}
```

5.5.4 Theorem

This document class does not define its own theorem environments, the defaults, supplied by the L^AT_EX kernel (`ltthm.dtx`) are available.

5.6 Setting parameters for existing environments

5.6.1 Array and tabular

`\arraycolsep` The columns in an array environment are separated by $2\arraycolsep$.

```
329 \setlength\arraycolsep{5\p@}
```

`\tabcolsep` The columns in an tabular environment are separated by $2\tabcolsep$.

```
330 \setlength\tabcolsep{6\p@}
```

`\arrayrulewidth` The width of vertical rules in the array and tabular environments is given by `\arrayrulewidth`.

```
331 \setlength\arrayrulewidth{.4\p@}
```

`\doublerulesep` The space between adjacent rules in the array and tabular environments is given by `\doublerulesep`.

```
332 \setlength\doublerulesep{2\p@}
```

5.6.2 Tabbing

`\tabbingsep` This controls the space that the `\`` command puts in. (See L^AT_EX manual for an explanation.)

```
333 \setlength\tabbingsep{\labelsep}
```

5.6.3 Minipage

`\@minipagerestore` The macro `\@minipagerestore` is called upon entry to a minipage environment to set up things that are to be handled differently inside a minipage environment. In the current styles, it does nothing.

`\@mpfootins` Minipages have their own footnotes; `\skip\@mpfootins` plays same rôle for footnotes in a minipage as `\skip\footins` does for ordinary footnotes.

```
334 \skip\@mpfootins = \skip\footins
```

5.6.4 Framed boxes

`\fboxsep` The space left by `\fbox` and `\framebox` between the box and the text in it.

`\fboxrule` The width of the rules in the box made by `\fbox` and `\framebox`.

```
335 \setlength\fboxsep{3\p@}  
336 \setlength\fboxrule{.4\p@}
```

5.6.5 Equation and eqnarray

`\theequation` The equation counter will be typeset using arabic numbers.

```
337 \renewcommand\theequation{\@arabic\c@equation}
```

`\jot` `\jot` is the extra space added between lines of an eqnarray environment. The default value is used.

```
338 % \setlength\jot{3pt}
```

`\@eqnnum` The macro `\@eqnnum` defines how equation numbers are to appear in equations. Again the default is used.

```
339 % \def\@eqnnum{(\theequation)}
```

5.7 Font changing

Here we supply the declarative font changing commands that were common in L^AT_EX version 2.09 and earlier. These commands work in text mode *and* in math mode. They are provided for compatibility, but one should start using the `\text...` and `\math...` commands instead. These commands are redefined using `\@renewfontswitch`, a command with three arguments: the user command to be defined; L^AT_EX commands to execute in text mode and L^AT_EX commands to execute in math mode.

`\rm` The commands to change the family.

```
340 \DeclareOldFontCommand{\rm}{\normalfont\rmfamily}{\mathrm}  
341 \DeclareOldFontCommand{\sf}{\normalfont\sffamily}{\mathsf}  
342 \DeclareOldFontCommand{\tt}{\normalfont\ttfamily}{\mathtt}
```

`\bf` The command to change to the bold series. One should use `\mdseries` to explicitly switch back to medium series.

```
343 \DeclareOldFontCommand{\bf}{\normalfont\bfseries}{\mathbf}
```

`\sl` And the commands to change the shape of the font. The slanted and small caps `\it` shapes are not available by default as math alphabets, so those changes do nothing `\sc` in math mode. One should use `\upshape` to explicitly change back to the upright shape.

```
344 \DeclareOldFontCommand{\it}{\normalfont\itshape}{\mathit}  
345 \DeclareOldFontCommand{\sl}{\normalfont\slshape}{\relax}  
346 \DeclareOldFontCommand{\sc}{\normalfont\scshape}{\relax}
```

`\cal` The commands `\cal` and `\mit` should only be used in math mode, outside math `\mit` mode they have no effect. Currently the New Font Selection Scheme defines these commands to generate warning messages. Therefore we have to define them ‘by hand’.

```
347 \ DeclareRobustCommand*\{\cal\}{\@fontswitch{\relax}{\mathcal}}  
348 \ DeclareRobustCommand*\{\mit\}{\@fontswitch{\relax}{\mathnormal}}
```

5.8 Footnotes

`\footnoterule` Usually, footnotes are separated from the main body of the text by a small rule. This rule is drawn by the macro `\footnoterule`. We have to make sure that the rule takes no vertical space (see `plain.tex`) so we compensate for the natural height of the rule of 0.4pt by adding the right amount of vertical skip.

To prevent the rule from colliding with the footnote we first add a little negative vertical skip, then we put the rule and make sure we end up at the same point where we began this operation.

```
349 \renewcommand\footnoterule{%
350   \kern-\p@
351   \hrule \width .4\columnwidth
352   \kern .6\p@}
```

`\c@footnote` A counter for footnotes.

```
353 % \newcounter{footnote}
```

`\@makefntext` The footnote mechanism of L^AT_EX calls the macro `\@makefntext` to produce the actual footnote. The macro gets the text of the footnote as its argument and should use `\@makefnmark` to produce the mark of the footnote. The macro `\@makefntext` is called when effectively inside a `\parbox` of width `\columnwidth` (i.e., with `\hsize = \columnwidth`).

An example of what can be achieved is given by the following piece of T_EX code.

```
\long\def\@makefntext#1{%
  \setpar{\@par
    \tempdima = \hsize
    \advance\tempdima-10pt
    \parshape \one 10pt \tempdima}%
  \par
  \parindent 1em\noindent
  \hb@xt@.z@{\hss\@makefnmark}#1}
```

The effect of this definition is that all lines of the footnote are indented by 10pt, while the first line of a new paragraph is indented by 1em. To change these dimensions, just substitute the desired value for ‘10pt’ (in both places) or ‘1em’. The mark is flush right against the footnote.

In this document class we use a simpler macro, in which the footnote text is set like an ordinary text paragraph, with no indentation except on the first line of a paragraph, and the first line of the footnote. Thus, all the macro must do is set `\parindent` to the appropriate value for succeeding paragraphs and put the proper indentation before the mark.

```
354 \newcommand\@makefntext[1]{%
355   \noindent
356   \hangindent 5\p@
357   \hb@xt@5\p@{\hss\@makefnmark}#1}
```

`\@makefnmark` The footnote markers that are printed in the text to point to the footnotes should be produced by the macro `\@makefnmark`. We use the default definition for it.

```
358 %\renewcommand\@makefnmark{\hbox{$^{\{\atethemark\}}$}}
```

6 Initialization

6.1 Words

\ccname This document class is for documents prepared in the English language. To prepare \enclname a version for another language, various English words must be replaced. All the \pagename English words that require replacement are defined below in command names.
\headtoname 359 \newcommand*\ccname{cc}
360 \newcommand*\enclname{encl}
361 \newcommand*\pagename{Page}
362 \newcommand*\headtoname{To}

6.2 Date

\today This macro uses the TeX primitives \month, \day and \year to provide the date of the LATEX-run.
363 \newcommand*\today{\ifcase\month\or
364 January\or February\or March\or April\or May\or June\or
365 July\or August\or September\or October\or November\or December\fi
366 \space\number\day, \number\year}

6.3 Two column mode

\columnsep This gives the distance between two columns in two column mode.
367 \setlength\columnsep{10\p@}

\columnseprule This gives the width of the rule between two columns in two column mode. We have no visible rule.
368 \setlength\columnseprule{0\p@}

6.4 The page style

We have *plain* pages in this document class by default. We use arabic page numbers.

369 \pagestyle{plain}
370 \pagenumbering{arabic}

6.5 Single or double sided printing

We don't try to make each page as long as all the others.

371 \raggedbottom

\@texttop The document class letter sets \@texttop to \vskip 0pt plus .00006fil on the first page of a letter, which centers a short letter on the page. This fil value may have to be changed for other letterheads. This setting has to be done after \raggedbottom is executed, since the latter sets \@texttop to \relax.
372 \def\@texttop{\ifnum\c@page=1\vskip \z@ plus.00006fil\relax\fi}

We always start in one column mode.

373 \onecolumn
374

Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols	
\@par	142, 161, 176
\auxout	147
\begin{parpenalty}	262
\bsphack	170
\colht	231
\colroom	231
\date	85, 92, 184, 189
\eha	30
\endparpenalty	262
\eqnnum	339
\espshack	170
\evenfoot	81, 83, 97, 113
\evenhead	81, 87, 97
\fontswitch	347, 348
\gobbletwo	250
\hangfrom	212, 217
\highpenalty	47
\ifstar	165, 172
\itempenalty	262
\latexerr	29
\listI	265
\listi	265
\listii	271
\listiii	271
\listiv	271
\listv	271
\listvi	271
\lowpenalty	47, 262, 263, 264
\mainaux	129, 131
\makefnmark	357, 358
\makefntext	354
\medpenalty	47
\minipagerestore	334
\mlabel	127, 148, 250
\mparswitchfalse	34
\mparswitchtrue	32
\mpfootins	334
\nobreakcr	162, 164
\nobreakvspace	163, 164
\nobreakvspace	164
\normalcr	172, 174
\oddfoot	81, 83, 90, 96, 100, 112
\oddhead	81, 84, 87, 91, 96, 99, 111
\onlypreamble	132
\@processsto	141, 151
\@ptsize	1, 25, 26, 27, 41, 102, 234
\@roman	290
\@startlabels	126, 129, 246
\@tempdima	22, 24, 69, 70, 71, 72
\@texttop	225, 372
\@thefnmark	358
\@twosidefalse	34
\@twosidetrue	32
\@unexpandable@protect	146
\@width	351
\@xproc	151
\@yproc	151
A	
\address	114, 121
\arraycolsep	329
\arrayrulewidth	331
\AtBeginDocument	125
\AtEndDocument	130
B	
\baselineskip	241
\baselinestretch	44
\bf	343
\bigskipamount	206
\boxmaxdepth	243
\brokenpenalty	56
C	
\c@enumi	288
\c@enumii	289
\c@enumiii	290
\c@enumiv	291
\c@equation	337
\c@footnote	139, 353
\c@page	135, 138, 372
\cal	347
\cc	209
\ccname	212, 359
\clearpage	131
\closing	195
\clubpenalty	50
\columnsep	233, 367
\columnseprule	368
\columnwidth	351
D	
\DeclareOldFontCommand	340, 341, 342, 343, 344, 345, 346
\DeclareRobustCommand	164, 347, 348
description (env.)	304
\descriptionlabel	306, 308
\displaywidowpenalty	52
\doublerulesep	332
E	
\encl	209
\enclname	217, 359
environments:	
description	304
letter	133
quotation	319
quote	325
verse	310
\evensidemargin	64, 229
\expandafter	192
F	
\fboxrule	335
\fboxsep	335
\footins	80, 334
\footnoterule	349
\footnotesep	79
\footnotesize	107, 239
\footskip	59
\fromaddress	116, 119, 182, 188, 198
\fromlocation	109, 117, 119
\fromname	114, 119, 203
\fromsig	115, 119, 202, 204
H	
\hb@xt@	101, 357
\headheight	57
\headsep	57, 227
\headtoname	84, 91, 359

	I	
\if@compatibility	\leftmarginv	\paperheight 4, 7, 10, 13, 16, 19, 22, 23
..... 28, 60, 64 251, 282, 283	\paperwidth
\if@files w 128, 131, 143	\leftmarginvi 5, 8, 11, 14, 17, 20, 23, 24, 69
\if@twoside 81, 135	letter (env.)	\parbox 200, 211, 216, 248
\ifodd	\lineskip	\parindent 45, 244
\ignorespaces	\listparindent	\parsep 266
..... 84, 91, 141, 187, 201, 213, 218, 248 314, 320, 321	\parskip 45, 188, 191, 193, 195, 206, 207, 208
\immediate 129, 131, 147	\location	\partopsep 261
\indentedwidth 179, 200	\longindentation	\postdisplaypenalty 52
\interlinepenalty 177, 181, 199	\predisplaypenalty . 52
..... 55, 140, 160, 175	M	\ps 209
\it	\makelabel	\ps@empty 95
\item 317, 323, 327	\makelabels	\ps@firstpage 98
\itemindent	\marginparpush	\ps@headings 81
..... 305, 313, 314, 321	\marginparsep	\ps@plain 110
\itemsep 268, 278, 312	\marginparwidth	
\itshape 344	\mathbf 343	Q
	\mathcal 347	quotation (env.) 319
	\mathit 344	quote (env.) 325
	\mathnormal 348	
J	\mathrm 340	
\jot 338	\mathsf 341	
	\mathtt 342	R
	\medskipamount 201, 206	\raggedleft 184, 187
L	\mit 347	\raisebox 100
\labelcount 222, 223	\mlabel 127, 247	\returnaddress 148, 221
\labelenumi 292	N	\rm 340
\labelenumii 292	\name 114, 119	
\labelenumiii 292	\newcount 222	S
\labelenumiv 292	\nobreakvspace 164	\sc 344
\labelitemfont 299, 300, 301, 302, 303	\normalfont	\scshape 346
\labelitemi 299 112, 113, 212, 217, 303, 309,	\sf 340
\labelitemii 299	340, 341, 342,	\sffamily 341
\labelitemiii 299	343, 344, 345, 346	\signature 114, 120
\labelitemiv 299	\normallineskip 42	\sl 344
\labelsep 258, 273, 276, 281, 284, 287, 308, 333	\normalsize 103, 235	\small 105, 237
\labelwidth 258, 272, 273, 275, 276, 280, 281, 283, 284, 286, 287, 305	\null 136	\smallskipamount 206
\leftmargin 251, 265, 271, 274, 279, 282, 285, 305, 315, 316, 322, 326	O	\startbreaks 173, 219
\leftmargini	\oddsidemargin 64, 228	\startlabels 126, 223
..... 251, 259, 265	\onecolumn 373	\stopbreaks 159, 196
\leftmarginii	\opening 182	\stopletter 142, 220
..... 251, 271, 272	\overfullrule 35, 36	\string 129, 131, 148
\leftmarginiii	P	\strut 204, 213, 218, 248
..... 251, 274, 275	\p@enumii 296	
\leftmarginiv	\p@enumiii 296	T
..... 251, 279, 280	\p@enumiv 296	\tabbingsep 333
	\pagebreak 142	\tabcolsep 330
	\pagename 86, 93, 359	\telephone 114, 123
	\pagENUMERATION 370	\telephonenum
	 109, 118, 119
		\textasteriskcentered 301
		\textbullet 299

\textendash	300	\theequation	337, 339	\tt	340
\textheight	62, 230, 231	\thepage	86, 93, 112, 113	\ttfamily	342
\textperiodcentered	302	\thispagestyle	\twocolumn	245
\textwidth 60, 71, 101, 178, 180, 211, 216, 232	\toaddress	148, 153, 157, 158, 192		V
\theenumi 288, 292, 296, 297	\today	363	\vadjust	170
\theenumii	288, 293, 297	\toname 84, 91, 148, 157, 192	verse (env.)	310
\theenumiii	288, 294, 298	\topmargin	78, 226	\vsize	231
\theenumiv	288, 295	\topsep	267, 277, 278		W
				\widowpenalty	50
				\write	129, 131, 147